# **Working with DNS Groups**

# **DNS Groups**

n	esources - DNS - DHCP - IP	AM - Peering - Reporting		Search or type he	elp
DNSv3 DNS	Groups DNS Servers	DNS Zones DNS Records			
NS Grou	os List Add Group				
DNS Groups help yo	u to organize all of your Zones and	d Servers together into a single pla	ice. With Groups, you are able to	p push whole group configurations.	
Resources Awaitir	ng Approval				>
Cefault Group					~
	Add Zone Push Group S	Schedule Push Export Zones	Perms		~
	Add Zone Push Group S Reverse Zones Catalog Zon		Perms		~
DNS Zones			Perms Zone Status	Actions T	~
Default Group     DNS Zones     Forward Zones     J <sup>1</sup> Zone Name     0.1.1.in-addr.arpa.	Reverse Zones Catalog Zon	nes		Actions 🔻	~
DNS Zones Forward Zones	Reverse Zones Catalog Zor Last Pushed	hes ↓† Last Modified	Records Zone Status		~
Forward Zones         Is Zone Name         0.1.1.in-addr.arpa.	Reverse Zones Catalog Zor Last Pushed 01/28/2019 15:02:34	Last Modified 02/21/2019 17:10:47	Records Zone Status	Delete Push Move Check Perms	

The DNS tab Groups List allows you to create, view, and manage groups of DNS Servers and Zones. Using groups, you can configure and push selected combinations of zones at one time.

- DNS Groups
  - DNS Groups List Interface
  - Working with DNS Groups
    - Add a Group
      - Create a Group
      - Navigating a Group
    - Edit a Group
      - Edit a Group Name
      - Edit Attached Servers
      - Edit a Group's Default Parameter Values
        - Edit Group Advanced Settings
        - Edit Nameservers
        - Edit Push Policy
        - Edit SOA Values
        - Save Changes
    - Add Zones to a Group
    - Pushing a Group
      - Manual Group Push
      - Scheduled Group Push
    - Delete a Group
    - Export a Group
    - Using the Templates Group / Cloning Zones to a Group
      - Create your template zone
      - Clone Template to a Different Group
    - Additional Information

## **DNS Groups List Interface**

DNS Grou	ps List Add Group					
DNS Groups help yo	ou to organize all of your Zones a	nd Servers together into a sing	gle place. With (	Groups, you are able	to push whole group configurations.	
Resources Awaitin	ng Approval					>
× Default Group						>
× Autogenerator	Group					>
X Example Group	)					*
DNS Zones	Add Zone Push Group	Schedule Push Export	Zones	ms		
Resources Awa	iting Approval					>
Forward Zones	Reverse Zones					
J <sup>®</sup> <sub>2</sub> Zone Name	Last Pushed	↓î Last Modified	Records	Zone Status	Actions T	
6connect.com.	01/28/2019 13:15:05	02/20/2019 14:14:11	2		Delete Push Move Check Perms	
6connectqa.com.	01/28/2019 13:15:05	02/20/2019 14:14:19	1		Delete Push Move Check Perms	
example.com.	01/28/2019 13:15:06	02/20/2019 14:14:22	0		Delete Push Move Check Perms	
Attached Serve	rs					>
Group Default F	Parameters					>
Applied ACLs						>
Catalog Zones	settings					>
Scheduled Task	s					>

#### 1) Add Group Button: Opens a dialog for creating a DNS Group

2) Resources Awaiting Approval Module - Group Level: Lists pending DNS Group level Approval events either submitted by, or able to be approved/rejected by, the current user.

3) Group Container: The Group container header shows the group name. Expand or close the group container by clicking on the expansion arrow (>) on the far right of the header. Clicking on the X will delete the Group and all zones included in the group. Rename the group by clicking on the name, then typing the desired changes and clicking outside of the name.

#### **Group Actions:**

X Default Group	~
DNS Zones Add Zone Push Group Schedule Push Export Zones Perms	

4) Add Zone Button: Opens a dialog for creating a DNS zone under that group.

5) Push Group Button: Pushes all zones in the group.

6) Schedule Push Button: Schedules a push of all zones in the group to the selected day and time. Requires the scheduler tab / cron tasks to be enabled.

7) Export Zones: Exports all zones in the group into a .zip file.

8) Perms (Admin): Provides a shortcut for Admin users to change the group/user permissions for the DNS Group.

9) Resources Awaiting Approval Module - Zone List Level: Lists pending DNS Zone List level Approval events either submitted by, or able to be approved/rejected by, the current user.

10) Zone List: Forward and reverse zones included in the Group.

11) Forward / Reverse Zones Tabs: Shows zone list containing only forward or reverse zones, respectively.

**12)** Zone Name (Sortable): The name of the zone. Clicking on the zone name will open the zone details window, showing individual records. Clicking on the "Zone Name" header will sort the zone list by ascending or descending by name.

13) Last Pushed: The date and time the zone was last pushed.

14) Last Modified (Sortable). The date and time the zone was last modified. Clicking on the "Last Modified" header will sort the zone list by most / least recent modification date.

15) Records: How many records are in the zone.

**16) Zone Status:** Will notify if the zone or server connection contains errors, after a check has been performed (by clicking on the "Check" button). Clicking on the "Contains Errors" message will provide additional details on the error.

17) Actions: The actions that may be performed on each zone:

Actions	Ŧ				
Delete	Push	Move	Check	Perms	

**18) Delete:** Deletes the zone from ProVision and removes the entry in ProVision conf file on the remote server(s) (the user will also receive a prompt to confirm they wish to complete the action)

- 19) Push: Pushes the zone to the associated server.
- 20) Move: Moves the zone to a different Group.
- 21) Check: Performs a check on the zone, notifying the user if errors or warnings are present for the zone.
- 22) Perms (Admin): Provides a shortcut for Admin users to change the group/user permissions for the zone.

23) Attached Servers: Sets the server that zone and group pushes will be sent to. Click on the header title or > to expand or collapse. Admins and users with server/group parent permissions may view, attach, or detach a server from the group.

24) Group Default Parameters: Click on the header title or > to expand or collapse. Edit default group settings including nameservers, SOA values, and Push Policy.

25) Applied ACLs: Click on the header title or > to expand or collapse. Add or detach ACLs to the group.

**26) Catalog Zone Settings:** Click on the header title or > to expand or collapse. Enable / Disable Catalog Zones. Enabling Catalog Zone exports all zones inside the Group into a new catalog zone, so that slave servers can receive zone changes.

27) Scheduled Tasks: If a scheduled push has been set up for the group, the task information will show in a "Scheduled Tasks" module. Click on the header title or > to expand or collapse. Review or delete scheduled group pushes.

## Working with DNS Groups

DNS Groups allow for organizing multiple zones together and linking those zones with one or more servers. Default nameservers, SOA values, and ACL's are set at the Group level, so different Groups may have their own default values. Zones may be pushed individually, as a Group, or at the server level.

ProVision automatically designates a Default Group for zones to be imported or added to, as well as a "templates" group for holding pre-DNSv3 templates or to hold new zones created as templates. Creating additional Groups is completely optional.

### Add a Group

DNSv3 automatically contains two Groups - one Default Group to contain existing or imported zones, and a Templates Group, containing zones mimicking DNS Templates. Additional Groups may be added or removed at any time, and zones may be freely moved or duplicated between different groups as needed.

To create a new Group, from the DNS Tab, select the DNS Groups sub menu. Then, click the "Add Group" button next to "DNS Groups List".



This will open the "Create New Group" dialog.

## **Create a Group**

In the "Create New Group" dialog, enter the desired Group Name, select a parent resource, enter the default SOA values, and add a default Nameserver (type the NS, then click "Add").

			_
DI	Create New Group		×
ONS	Group Name:	aNewGroup	
4	Parent Resource:	TLR	•
	Default SOA Value	S	
ull of	The values supplied her	e are the default SOA values used on all newly created zones.	
	SOA Host:	ns.example.com.	
	SOA Mail:	hostmaster.example.com.	
F	Refresh:	172800	
es	Retry:	900	
st F	Expire:	1209600	
/22/	Minimum:	900	
	TTL:	1 hour 🗘	
	Default Nameserve	ers	
	The name servers are a	utomatically added to any new zone files created.	
	NameServer:	ns1.example.com Add	
/27/	Order	NS Record	
I.	1	ns1.example.com.	
		Close Save change	es

Click the "Save Changes" button when complete. The new group will be added to the DNS Groups List.

## **Navigating a Group**

Open the Group container for the new Group by clicking on the expansion arrow at the top right corner of the header.

Information for Attached Servers, Group Default Parameters, Applied ACLs, and Catalog Zones settings may also be viewed and edited by clicking on the expansion arrows for each section.

X aaNewGroup					·
DNS Zones	Add Zone Push Group	Schedule Push Export Zones P	erms		
Forward Zones	Reverse Zones				
$\downarrow_z^{\scriptscriptstyle B}$ Zone Name	Last Pushed	$\downarrow \uparrow$ Last Modified	Records	Zone Status	Actions <b>T</b>
Attached Serve	rs				$\rightarrow$
Group Default F	Parameters				>
Applied ACLs					>
Catalog Zones	settings				$\rightarrow$

## Edit a Group

### **Edit a Group Name**

Edit the name for a Group by clicking inside the Group's Name. A highlight box will appear around the name, and a cursor inside the box.

# × aNewGroup

Edit the text as desired using your mouse or arrow keys to navigate through the text. When complete, click anywhere outside of the name box, and a confirmation dialog will appear.

ישי	Please confirm.	×
ינ /2	Are you sure that you want to rename "aNewGroup" to "NewGroup".	
	Confirm Close	•

Click "Confirm" to save your changes, or "Close" to exit without saving.

### **Edit Attached Servers**

Users may attach or detach servers from a group if they have either of the following permission types:

- TLR Admin permissions
- Full permissions on both the DNS Server(s) and the Parent Resource set for the DNS Group

If either condition is met, the user may view and attach/detach the applicable server(s) to a Group.

To attach a server, expand the "Attached Server" module, and click on the Attach Server list.

Attached Servers				$\checkmark$
Server Name	Server Backend	Server Type	Server Status	Actions
Attach server : Select Server	Attach			

Select the desired server, then click "Attach".

Attached Servers				~
Server Name	Server Backend	Server Type	Server Status	Actions
Attach server : BIND 6c	connect QA Server	$\triangleright$		

The server is now attached to the group, and future zone and group pushes will be sent to the attached server.

Attached Servers					~
Server Name	Server Backend	Server Type	Server Status	Actions	
BIND 6connect QA Server	ISCBIND	master		Detach Perms	
Attach server : Select Server	♦ Attach				

From here, users have the option to Detach the server if desired, by clicking the "Detach" button.

Admin users may edit pemissions for the server using the "Perms" button, if desired (see: DNS Tab DNSv3 Permissions for additional information).

Attached Servers				~	
Server Name	Server Backend	Server Type	Server Status	Actions	
BIND 6connect QA Server	ISCBIND	master		Detach Perms	
Attach server : Select Server	♦ Attach				

### **Edit a Group's Default Parameter Values**

Under the desired Group, expand the "Group Default Parameters" module by clicking on the expansion arrow.

Group Default Parameters	$\diamond$
Save your changes!	
Important - to ensure that your changes are saved while working in Group Default Par under the Default SOA Values section - this save button will save any changes made to Default SOA Settings.	
Push Policy changes can be saved by clicking "Save Push Policy".	

.

### **Edit Group Advanced Settings**

Open the "Advanced Settings Inherited by the Zones" module by going to any DNS Group and opening the "Group Default Parameters".

The Advanced Settings module will be at the top of Default Parameters area. To expand it, click on the expansion arrow on the right side of the header bar.

Advanced	Settings Inherited by	<u>y the Zones</u>			
Default Nameservers Default SOA Values					
The name servers are automatically added to any new zone files created.		The values suppl newly created zo	lied here are the default SOA valu ones.	es used on all	
NameServer:	enter NS record	Add	Parent TLR Resource:		•
			nesource.		

Once expanded, settings may be entered for DNSSEC, Dynamic Updates, Master-Slave Handling, Lists, and free lines.

Enable Dynamic Update Disable Master-Slave handlin Also-Notify Lis Allow Update Lis	Section 2017 Sect
Disable Master-Slave handlin Also-Notify Lis	This feature is using the dynamic update functionality of the DNS Server. Every record that you modify/remove/create will b updated on the servers automatically without pushing the zone if the queue is not enabled.      GOFF     By default ProVision handles the master and slave specific options in the zone automatically. By enabling this option ProVision will not add specific configuration options to the zone depending on the server configuration.      ex. 192.168.3.0; 10.10.3.0/24      The list will be added to the also-notify list on the DNS servers that support this option.
Also-Notify Lit	updated on the servers automatically without pushing the zone if the queue is not enabled.         g:       OFF         By default ProVision handles the master and slave specific options in the zone automatically. By enabling this option ProVision will not add specific configuration options to the zone depending on the server configuration.         st:       ex. 192.168.3.0; 10.10.3.0/24         The list will be added to the also-notify list on the DNS servers that support this option.
Also-Notify Lit	By default ProVision handles the master and slave specific options in the zone automatically. By enabling this option ProVision will not add specific configuration options to the zone depending on the server configuration.         st:       ex. 192.168.3.0; 10.10.3.0/24         The list will be added to the also-notify list on the DNS servers that support this option.
·	ProVision will not add specific configuration options to the zone depending on the server configuration.  ex. 192.168.3.0; 10.10.3.0/24 The list will be added to the also-notify list on the DNS servers that support this option.
	The list will be added to the also-notify list on the DNS servers that support this option.
Allow Update Lis	· · · ·
Allow Update Lis	st: ex. 192.168.3.0; 10.10.3.0/24
	The list will be added to the allow-update list on the DNS servers that support this option.
Allow Transfer Lis	st: ex. 192.168.3.0;
	The list will be added to the allow-transfer list on the DNS servers that support this option. On exporting a zone to a master server, the slaves are automatically added !
Allow Notify Lis	st: ex. 10.1.0.15; 172.28.32.7;
	The list will be added to the allow-notify list on the DNS servers that support this option. On exporting a zone to a slave server, the masters are automatically added !
Free Lines (Dangerous	s): test
	The content inside this field will be append to the zone section of the server configuration. Please be very careful with this field as it can cause configuration errors ! They are currently valid only for ISC Bind.
Server Specific Free Line (Dangerous	

#### A Save your changes!

Important - to ensure that your changes are saved, click the "Save Group Defaults" button under the Default SOA Values section - this save button will save any changes made to Advanced Settings, Default Nameservers, or Default SOA Settings.

Server Specific Free (Dang	BIND 6connect QA Server (GOOD) \$	Add new	
Default Nameserve	rs	Default SOA	A Values
he name servers are automatical	ly added to any new zone files created.	The values supplied zones.	here are the default SOA values used on all newly created
Order NS Record		Parent Resource:	TLR *
1 ns1.examp	le.com. X	SOA Host:	ns1.indianafiber.net.
Push Policy		SOA Mail:	hostmaster.indianafiber.net.
	ones and modules will be handled on Push	Refresh:	3600
Group Centric		Retry:	3601
ush all the zones in the group to	the servers attached to the group.	Expire:	604800
Zone Centric		Minimum:	3600
ush all the zones in the group to ot attached to the group.	all the servers attached to them including servers	TTL:	30 minutes
Server Centric			
ush all the servers in the group t ot attached to the group.	o all the zones attached to them including zones	C	Save Group Defaults

### **Edit Nameservers**

Default Nameservers are automatically added to any newly created zone files.

You may choose not to set a default nameserver, however, an empty Nameservers list can cause invalid zones.

Change a Nameserver by typing the new NS record into the Nameserver box, then click "Add".

Group Defaul	t Parameters	
Default N	lameservers	
The name serve	rs are automatically added to any new zon	e files created.
NameServer:	ns2.example.com.	
Order	NS Record	
1	ns1.example.com.	×

Delete the previous Nameserver by clicking on the red "X" to the right of the NS Record.

Group Delat	It Parameters	
Default	Nameservers	
The name serv	ers are automatically added to any new z	one files created.
NameServer	ns2.example.com.	
Order	NS Record	
1	ns1.example.com.	×
2	ns2.example.com.	×

Change the order of multiple Nameservers by left-clicking (holding the mouse button down) over the NS Record to move, dragging to its desired placement, then releasing the mouse button.

The NS record will drop into its new location, with the order updated.

The name serve	ers are automatical	ly added to any new zone fil	es created.		
NameServer:	ns1.6connect.com	Add			
Order	NS Record				
	2	ns2.example.com.		×	
1	ns1.6connec	et.com.	×		

### **Edit Push Policy**

Edit the push policy by selecting the radio next to the desired push behavior ("Group Centric", "Zone Centric", or "Server Centric") and click "Save Push Policy".

## **Push Policy**

The Push Policy determine what zones and modules will be handled on Push action.

#### Group Centric

Push all the zones in the group to the servers attached to the group.

#### **Zone Centric**

Push all the zones in the group to all the servers attached to them including servers not attached to the group.

#### **○ Server Centric**

Push all the servers in the group to all the zones attached to them including zones not attached to the group.



### **Edit SOA Values**

To edit the Default SOA values, simply click inside the value to be changed and type or select your new value. Be sure to also verify the desired Parent Resource for the Group, as the resource selected determines the Group's permissions.

## **Default SOA Values**

The values supplied here are the default SOA values used on all newly created zones.

Parent Resource:	TLR -	
nesource.		
SOA Host:	ns.example.com.	
SOA Mail:	hostmaster.example.com.	
Refresh:	172800	
Retry:	900	
Expire:	1209600	
Minimum:	900	
TTL:	1 hour \$	
	Save Group Defaults	

### **Save Changes**

Save all Nameserver, Advanced Settings, and SOA value changes by clicking on the "Save Group Defaults" button at the bottom of the section.

Closing without saving will cause all changes to be lost.

Server Specific Free Lines (Dangerous):	BIND 6connect QA Server (GOOD)	Add new		
Default Nameservers		Default SOA	Values	
The name servers are automatically added	to any new zone files created.	The values supplied I zones.	here are the default SOA values used	on all newly created
Order NS Record		Parent Resource:	TLR	•
1 ns1.example.com.	×	SOA Host:	ns1.indianafiber.net.	
Push Policy		SOA Mail:	hostmaster.indianafiber.net.	
The Push Policy determine what zones and action.	modules will be handled on Push	Refresh:	3600	
Group Centric		Retry:	3601	
Push all the zones in the group to the serve	rs attached to the group.	Expire:	604800	
Zone Centric		Minimum:	3600	
Push all the zones in the group to all the ser ot attached to the group.	vers attached to them including servers	TTL:	30 minutes	\$
Server Centric				
Push all the servers in the group to all the z not attached to the group.	ones attached to them including zones		Save Group Defaults	

## Add Zones to a Group

To add a new zone to a Group, click the "Add Zone" button inside the desired Group.

X Default Group	*
DNS Zones Add Zone Push Group Schedule Push Export Zones Perms	

Fill in the zone name, select a parent resource (by default, the Group is selected), select a populate type, and fill in any optional fields.

For more detail on each of these options, see Working with DNS Zones - Add a Zone.

R	Create New Zone			×	Se
Gro	Zone Name:	someZone2.com.		•	
DS	DNS Group:	Default Group			
ı to	Parent Resource:	Default Group			o pu
l	Populate with reco	ords			
	Populate type:	Empty Zone		¢	
R	Optional Fields			>	
La					
0			Close	Save changes	h

When complete, hit the "Save Changes" button.

## Pushing a Group

Before pushing a group for the first time, verify the settings in the following areas are correct:

- Under "Attached Servers", verify that the correct server is attached to the DNS Group.
  Under "Group Default Parameters" verify SOA Settings, Nameservers, and the Push Policy are set.

### **Manual Group Push**

After verifying the attached server and group settings, manually push the Group by clicking the "Push Group" button under the desired Group.

× Default Group	*
DNS Zones Add Zone Push Group Schedule Push Export Zones Perms	

A DNS Push Status window appears, showing each zone in the Group as it is pushed to the attached server. If successful, a green "Finished DNS Pushing Request" will appear as the final message. If errors occur, an error message will show with details on the issue. When complete, hit the "Close" button.

DNS Push Status	×
Last status messages :	
Finished DNS Pushing Request	
Sending the global configs and closing the connection	
Pushing zone "someZone2.com."	
Pushing zone "someZone.com."	
Cleaning the removed zones from the server	
Initializing the connection Server "6c BIND QA Server"	
DNS Pushing started	sh
	sh
	Close

## **Scheduled Group Push**

Scheduled pushes may be set up through the "Schedule Push" button for the Group.

× Default Group	<b>~</b>
DNS Zones Add Zone Push Group Schedule Push Export Zones	Perms

Click "Schedule Push" for the Group, then select a date, time (12 hour, with AM / PM toggle), add a notification email address, and click "Save changes".

Pus	h Sche	eduler						×
Pick date and time (US/Pacific):								
	<		Feb	oruary 20	19		>	
	Su	Мо	Tu	We	Th	Fr	Sa	
	27	28	29	30	31	1	2	
	3	4	5	6	7	8	9	
	10	11	12	13	14	15	16	1
	17	18	19	20 🖌	21	22	23	
	24	25	26	27	28	1	2	
	3	4	5	6	7	8	9	
		~		~				
		02	:	25		PM		
		~		~				
Notif	ication	Email:						
sor	mething	@examp	le.com					
					Close	Sav	ve chang	jes

The Scheduled task will be shown in both the Group details (under "Scheduled Tasks") and the Admin Scheduler task list.

Task Name	Last Run	Repeat Time	Actions
Scheduled Push: Default Group		One time on 2017-05-31 at 14:00 PDT	Delete

The task may be deleted prior to running by clicking the "delete" button, but will automatically be removed once completed.

## **Delete a Group**

Delete a non-Default Group by clicking on the "X" to the left of the Group's name in the DNS Groups List.



A confirmation message will appear, click "Confirm" to save your changes, or "Close" to exit without saving.

	Please confirm.	×
ł	Are you sure that you want to delete "Group 2a" and all the zones.	
	Confirm Clos	e

The Default Group may not be deleted.

## **Export a Group**

All zones under a DNS Group may be exported to a .zip file by clicking the "Export Zones" button at the top of the Group module.

The exported .zip file may be used with ProVision's BIND DNS Zone Upload / Import tool.

X Default Group	~
DNS Zones Add Zone Push Group Schedule Push Export Zones Perms	

## Using the Templates Group / Cloning Zones to a Group

By default, a "templates" group is included in DNSv3.

Any pre-DNSv3 DNS Templates will be included in this group, as well as any newly created zones to be used as template zones.

× templates							
DNS Zones Add Zone Push Group Schedule Push Export Zones Perms							
Forward Zones	Reverse Zones						
J <sup>R</sup> <sub>Z</sub> Zone Name	Last Pushed	$\downarrow \uparrow$ Last Modified	Records	Zone Status	Actions T		
Attached Serve	ers					>	
Group Default	Group Default Parameters						
Applied ACLs						>	
Catalog Zones	Catalog Zones settings						

The template group functions the same as any other DNS Group, but gives a holding place for zones designed as templates separate from other zones.

### **Create your template zone**

Add a template zone by clicking the "Add Zone" button, giving the zone a descriptive name to clearly identify as a template, select the populate type, and fill in any optional data. (see Working with DNS Zones - Add a Zone.)

Create New Zone		×
Zone Name:	someZoneTemplate.com.	
DNS Group:	templates	
Parent Resource:	templates	•
Populate with rec	ords	
Populate type:	Empty Zone	\$
u		
Optional Fields		>
P		
	Close Save chang	ges

Once the zone has been created, it will show in the templates group zone list, and is now selectable as a base for the "clone existing zone" option when creating a new zone.

## **Clone Template to a Different Group**

Go to a different group, and click "Add Zone". Enter in the new zone name and parent.

Under "Populate Type", select "Clone existing zone" and select /search for the template zone you created.

Ad	Create New Zone	2	<
ofy	Zone Name:	aZoneFromTemplate.com.	ou
	DNS Group:	Default Group	
Pu	Parent Resource:	Default Group -	
	Populate with reco	rds	
he	Populate type:	Clone existing zone	tio
17	Select Zone:	someZoneTemplate.com.	let
17	Skip Group NS:	ON	let
	Optional Fields	>	
		Close Save changes	

Edit the optional fields as needed, and click "Save changes".

## **Additional Information**

For more information on DNSv3 tasks, see:

- Working with DNS ZonesDNS Zones Overview
- DNS Administration
- Working with DNS Servers
  Approvals