

Importing Your Data

Preparing for Data Import

Before importing your data into ProVision, there are a few steps we recommend in order to make the import process as smooth as possible:

- Step 1: Normalize your Data
- Step 2: Prep your Data
- Step 3: Import your Data

Data Import Overview: Which Import Tool Should I Use?

- Resource Import
- Peering Import
- IP Import
- DNS Import
- Import Templates
- Additional Information

Step 1: Normalize your Data

Prior to importing your data, there is a key step of Data Normalization to ensure that information is accurate. If you need assistance with parsing your data prior to importing, 6connect can help with our Data Analyst service, just email us at support@6connect.com for more information. You can also use off the shelf tools like Microsoft Excel, MySQL, or [Google Refine](#) if you intend to take on the task of data cleanup in house.

Common normalization steps required for imports include:

- Remove any empty rows in the data range
- Remove any empty columns in the data range
- Remove stray data from inside and outside the data range, such as:
 - notes, comments, and placeholder text as field values, when not set as their own data column
 - nested secondary information located in additional rows under a primary record
- Ensure proper data formatting
 - Check for data formatting errors - a common issue is leading zeros being dropped from a ZIP field when a file is opened. Re-specify format as needed.
 - Ensure each field has consistent formatting for values
- Ensure unique values for primary identifiers, such as Resource Name and ID Fields


Data Encoding Format

To ensure correct importing of any special characters, make sure to use UTF-8 encoding for your CSV file!

Step 2: Prep your Data

You can download data import templates from the [Dashboard Tab](#) or [Data Import Tab](#). We recommend that you open the [CSV import templates](#) and get familiar with the data fields that you can import into the platform.

- **For Company information** you can import relevant data including mailing/billing address information as well as ARIN specific SWIP fields, and specific DNS servers.
- **For Contact information** you can import contact records assigned to a given [company](#). We support typical fields for this data including name, multiple email fields, phone numbers as well as timezone and role (roles can be customized from the [IPAM Admin tab](#)).
- **For IP Block information** you can import the following fields:



Allow Subassignments option

When importing the field "Allow Subassignments" - the parameters accepted are "TRUE", "1", "Y", "yes"

Step 3: Import your Data

Get to the **Data Import** Tab from the **Admin** button to import your data. For larger data import runs, feel free to contact support at any time for assistance.

Data Import

Import Tools

Information on preparing data for import and using each import tool is available at <https://docs.6connect.com/display/DOC/Importing+Your+Data>.
Sample import templates are available [here](#).
You can use 3rd party utility to verify the imported zones from [here](#).


Resource Import: Simple Upload/Import from CSV Resource Import Tool "Beta"	DNS Import: BIND Zone Upload/Import PowerDNS Zone Import InfoBlox Zone Import NS One Zone Import Dyn DNS Zone Import DNSMadeEasy Zone Import Route53 Zone Import IPPlan Zone Import
IP Import: Upload/Import from CSV Import from RIR	
Peering Import Import BGP Sessions	

Data Import Overview: Which Import Tool Should I Use?

Resource Import

Simple Upload / Import from CSV: Use this tool if you have a simple .csv file of customer / contact information, such as name, address, billing address, phone numbers, POC, etc. See [Resource Import from CSV](#) for more details.

This tool supports the following fields:



For Resource Import from .csv, the following fields are REQUIRED:

- Name (Unique Resource / Customer Name)
- Customer ID (Unique non-name identifier)

All other fields are optional.

Note: Resource Import from .csv currently only supports the columns above. For importing additional data, please see the Resource Import Tool, or contact support for details on import services.

Resource Import Tool: The Resource Import tool is designed for importing .csv files for any resource type (company, physical devices, contacts, customers, etc), and allows for customized headers through integrating ProVision's customizable sections and fields. It also allows for data editing within the tool.

Use the Resource Import Tool if you have resource data that does not fit under the [Simple Upload / Import from CSV](#) field options, and can equate that data to fields in an existing or newly created [Section](#).

Note: The Resource Import Tool currently supports field attributes which are able to be added to Section. High level resource information metadata (associated Parent, Category, etc) are outside the scope of this tool, but may be imported via the API or by custom import services. Contact support for additional assistance.

Additional Information


A tutorial / walkthrough for this tool is available at the [Resource Import Tool](#) page.

Peering Import

Import BGP Sessions: This section imports peering sessions from a selected exchange and router. Routers must be created prior to using this importer. See [Peering Routers](#) and [Importing Sessions](#) for additional information.

IP Import

Upload / Import from CSV: Use this tool if you have a .csv file of IP block information, such as CIDR, mask, ASN, RIR, etc. This tool supports the following fields:



For IP Import from .csv, the following fields are REQUIRED:

- CIDR String OR both IP and mask
- RIR OR a selected default RIR

All other fields are optional.

Import from RIR: This tool automatically lookups your ARIN or RIPE information based on the IP address you are connected to. Once it identifies the blocks assigned to your company, you can import both 1918 aggregates as well as public IP space from ARIN and RIPE. See [Import Aggregate Blocks](#) for more detail on this tool.

DNS Import

The following DNS Import options are available from the [Data Import](#) tab:

BIND Zone Upload / Import: Imports DNS zones using the named.conf configuration file tied to the zones you are uploading, a .zip or .tar file of the zones themselves, and an optional .csv file mapping zones to customers and DNS Servers. This is the simplest and most commonly used import method. Refer to [Import DNS Zones](#) for more information.

PowerDNS Zone Import: This tool is available after [configuring a PowerDNS server](#) with a MySQL backend. The PowerDNS Import connects to the selected server and imports all zones.

InfoBlox Zone Import: Imports DNS zones using a provided Host, Username, and Password. The InfoBlox import pulls all zones on the InfoBlox LOCAL grid and adds them to a designated Group. It is advised to [create a DNS Group](#) prior to the import with default parameters and NS records to be inherited by the imported records.

NS ONE Zone Import: Imports DNS zones using a NS One API Key. It is advised to [create a DNS Group](#) prior to the import with default parameters and NS records to be inherited by the imported records.

Dyn DNS Zone Import: Imports DNS zones using a Dyn DNS Customer Name, Username, and Password. It is advised to [create a DNS Group](#) prior to the import with default parameters and NS records to be inherited by the imported records.


DNSMadeEasy Zone Import: Imports DNS zones using a DNSMadeEasy API Key and API Secret. It is advised to [create a DNS Group](#) prior to the import with default parameters and NS records to be inherited by the imported records.

IPPlan Zone Import: Imports DNS zones using IPPlan MySQL database options. It is advised to [create a DNS Group](#) prior to the import with default parameters and NS records to be inherited by the imported records.

Additional DNS import options may be available on a per-zone or per-server level, accessed from the [DNS Tab](#):

DNS Zone Import: This tool is available on a zone's "View Zone" page, and allows the user to import additional zone/record information into an existing ProVision zone by uploading a zone file (.zone).

- From the View Zone page, a zone file (.zone) may be imported into a ProVision zone to populate record data. Click "Import Zone".



A Zone Import dialog box will open. Next to **Zone File:**, click "Choose File" and select your .zone file to import. Then, select an import policy to follow.

Zone Import

Zone Name: example.com.

Zone File: Choose File | No file chosen

Import Policy

- ☒ **Default Records Add**
The records with the same hosts but with different values will be added (useful for Load Balancing).
- ☐ **Skip records with the same host**
The import will skip adding records with hosts that already exists.
- ☐ **Remove the existing hosts from the zone. WARNING!**
If the import contains a host that already exists in the zone, the existing records will be removed from the zone and the imported record will be added.

Import Zone **Close**

When done, Click "Import Zone".

Import Templates

Import template sample files are available for selected ProVision import tools. A link is provided for a download page, both here and on the [Data Import](#) Tab.

These may be viewed as an example of .csv setup for their respective importers, or used for tutorials.

They are:

All Import Samples - Links to the [CSV import templates](#) page of the documentation, showing all available import template .csv files.

IP Import Sample File - Download the IP-import-sample_v1.csv file from the import templates page linked above, used in the [IP Import: Upload / Import from CSV](#) Tool.

Customer Sample Import - Download the customer-import-sample.csv file from the import templates page linked above, used in the [Resource Import: Simple Upload / Import from CSV](#) Tool.

Additional Information

For more details, see:

- [Resource Import from CSV](#)
- [Resource Import Tool](#)
- [Import Peering Sessions](#)
- [IP Import from CSV](#)
- [Import Aggregate Blocks](#)
- [Import DNS Zones](#)