

Working with IP Aggregates

Working with IP Aggregates

IPAMv2 IPAM VLAN Logging

Manage aggregate

16.0.0.0/12 - ARIN Switch to Parent view export to CSV actions + Search within this aggregate Q clear filter >

IP Address	IP Host	IP LIR	IP Region	IP Tags	IP Notes	IP Assigned to	IP ...	IP VLAN	IP A...	IP Updated	IP NAT	IP Meta1
16.0.0.0/14	262144	ARIN Default...	Denver, CO	Customer	-	Some Co.	-	3	8038	2019-07-30	-	-
16.4.0.0/16	65536	ARIN Default...	Denver, CO	Customer	-	available	-	3	8038	2019-07-25	-	-
16.5.0.0/22	1024	ARIN Default...	Denver, CO	Customer	-	available	-	3	8038	2019-07-30	-	-
16.5.4.0/22	1024	ARIN Default...	Denver, CO	Customer	-	available	-	3	8038	2019-07-30	-	-
16.5.8.0/21	2048	ARIN Default...	Denver, CO	Customer,Generic Tag	Some Note	A Customer	-	-	8038	2019-07-30	-	Some Inf...
16.5.16.0/20	4096	ARIN Default...	Denver, CO	Customer,Generic Tag	Some Note	A Customer	-	-	8038	2019-07-30	-	Some Inf...
16.5.32.0/19	8192	ARIN Default...	Denver, CO	Customer	Some Note	available	-	-	8038	2019-07-25	-	Some Inf...

IPAM Aggregates

IP Aggregates are edited and managed from the [IPAM](#) Tab and IPAM Manage page.

Aggregates may be viewed, filtered, created, and deleted from the [IPAM](#) Tab, and setting IPAM alerts and using Aggregate Templates are performed in IPAM Manage.


For an overview of the IPAM Tab, see [IPAM Tab](#). For information on working with individual blocks, continue to [Working with IP Blocks](#).

- [Working with IP Aggregates](#)
- [Working with IP Aggregates - Common Tasks](#)
 - [Add an Aggregate](#)
 - [Delete an Aggregate](#)
 - [Merge Aggregates](#)
 - [Sparse Allocate in an IPv6 Aggregate](#)
 - [Sparse Allocation Schemes](#)
 - [Enable/Disable Sparse Allocation](#)
 - [Sparse Allocate](#)
 - [Manage an Aggregate](#)
 - [Open IPAM Manage for an Aggregate](#)
 - [Aggregate Actions](#)
 - [Auto Split Aggregate](#)
 - [Clean Up Aggregate](#)
 - [Set Aggregate Alerts](#)
- [Working with IP Blocks](#)
- [Additional Information](#)

Working with IP Aggregates - Common Tasks

Add an Aggregate

On the main [IPAM](#) Tab, click the "Add Aggregate" button. A new page will open to fill in details for a new aggregate block.



Enter in the desired IPv6 / IPv6 CIDR and RIR, at minimum. Region, Tags, Resource, Domain, VLAN, and subassignment status are optional, if desired.

The screenshot shows the 'Add aggregate' form with the following fields:


- Subnet ***: x.x.x.x/yy OR xxxxxxxx:xxxx:yyyy
- RIR ***: RIR
- Region**: Region
- Tags**: Select tags...
- Resource**: assign a resource...
- Domain**: select a domain
- VLAN**: (empty)
- Allow sub assignments**: OFF
- Add aggregate** button

If creating the aggregate for a specific use, keep in mind that certain uses may require additional information is provided in the aggregate, such as requiring 1918 space (DHCP Pools), a region to be provided (DHCP Customer Configuration Gadget), or a resource to be assigned with subassignments enabled. In such cases, it may be useful to assign a specific IPAM tag to associate with that use to assign at aggregate creation (such as "DHCP")

When done, click "Add Aggregate", and you will be redirected back to the IPAM Tab home page. The Aggregate will be listed under the Host Utilization and Aggregate Blocks list of the IPAM Tab.

Delete an Aggregate

Aggregates may be deleted from the Gear Icon in the top right corner of their Host Utilization box display.




A warning dialog box will appear confirming the deletion, and noting whether assigned blocks exist in the aggregate that would also be deleted.


Merge Aggregates

Adjacent Top Level Aggregates may be merged into a single aggregate, if meeting validity criteria (adjacent, but not overlapping).


To do so, right click anywhere on the Aggregate Blocks list, and choose "Select Aggregates" from the menu.



Then, click the check boxes for the two aggregates you wish to merge, and then right click and select "Merge Selection".




A confirmation dialog box appears to confirm the blocks to merge, and proceed with testing to see if the merge is valid. Click "Test Merge" to proceed.



ProVision will pre-test the merge, and if valid, give you the option to proceed.

Otherwise, an error message will display detailing why the aggregates are unable to be merged.



Complete the aggregate merge by clicking "Merge".

To Exit out of the selection prior to merging, select "Close".

Sparse Allocate in an IPv6 Aggregate

Sparse allocation evenly distributes assignments throughout an IPv6 range, using either a manually configured or automatically generated "Sparse Allocate" Numbering Authority domain algorithm to calculate the next block to assign.

Sparse Allocation Schemes

Admins may select a system default Sparse Allocation scheme to use for IPv6 Sparse Allocation. Available values are Leftmost, Center, and Rightmost. If not otherwise specified, Leftmost is the ProVision Default.

To edit the Sparse Allocation Scheme, select the desired scheme in [IPAM Configuration](#), then enable sparse allocation for the desired IPv6 aggregate. The Sparse allocation scheme is applied to the aggregate when sparse allocation is enabled for the aggregate, thus, pre-existing sparse allocation schemes will not be altered by later changes.

IPAM Configuration

Holding Tank Days	<input type="text" value="0"/>
IPv4 Block Scanner Enable	<input checked="" type="checkbox"/>
IPv4 Block Scanner Max Block Size	<input type="text" value="/20"/>
RIPE Database	<input checked="" type="radio"/> RIPE <input type="radio"/> TEST
Show /32 or /128 mask for statics	<input checked="" type="checkbox"/>
Merge after unassign	<input checked="" type="checkbox"/>
Automatic Merge respects Tags & Regions	<input checked="" type="checkbox"/>
Enable Map View	<input checked="" type="checkbox"/>
Default Tag Selection Mode	<input checked="" type="radio"/> Standard <input type="radio"/> Strict <input type="radio"/> Exclude
Sparse Allocation Block Size	<input type="text" value="/64"/>
Sparse Allocation Type	<input type="text" value="Leftmost"/>

[Update](#)[Back To IPAM Admin](#)

When enabled, ProVision will automatically merge unassigned blocks into the largest possible block within an aggregate

When enabled, the automatic merge performed after an unassign will stop if the two blocks do not have identical tags and regions.

If you wish to change the scheme for an existing sparse allocated-enabled aggregate, you must

- 1) Disable sparse allocation for the aggregate
- 2) Edit the selected scheme
- 3) re-enable sparse allocate for the aggregate.

To verify which scheme is applied to aggregates, you may view the aggregate and scheme details in the [Numbering Authority](#) Sparse Allocate listings.

Numbering Authority

Numbering Authority is a configurable set of values and the associated functions to track which values have been handed out and which are still available.


Create New Numbering Domain

Filter by Type:

↕ Name	↕ Reuse values	↕ Type	Actions
Automatic Numbering Domain for IP Id: 34169	Yes	IPv6 Sparse Allocation	Get Next Value View Assigned Values Delete
		Starting IPv6: ABCD:EF01:2345:: Starting Block Prefix: 48 Increments: 64 Allocation type: undefined	
Automatic Numbering Domain for IP Id: 34871	Yes	IPv6 Sparse Allocation	Get Next Value View Assigned Values Delete
		Starting IPv6: AAAA:BBBB:2345:: Starting Block Prefix: 48 Increments: 64 Allocation type: undefined	
Automatic Numbering Domain for IP Id: 6267	Yes	IPv6 Sparse Allocation	Get Next Value View Assigned Values Delete
		Starting IPv6: 2001:506:6000:: Starting Block Prefix: 35 Increments: 64 Allocation type: leftmost	

Enable/Disable Sparse Allocation

Sparse allocation options are accessed from the IPv6 Aggregate's Action Menu (gear icon). The top right corner of the Utilization module for the IPv6 aggregate will display whether sparse allocation is enabled or disabled for the particular aggregate.




Enable or disable Sparse Allocation for the aggregate by clicking on the aggregate menu, and select to Enable / Disable Sparse Allocation for the aggregate. A "Sparse Allocate" Numbering Domain will automatically be generated for the aggregate in the Admin [IPAM Admin](#) area of ProVision, using the currently set Sparse Allocation Scheme setting.

Once enabled, the "Sparse Allocate" option will be available for the aggregate.

Sparse Allocate

To Sparse Allocate assign the next IP generated, select "Sparse Allocate" from the aggregate action menu.



Then, select the resource to assign (or create a new one) and click "Assign".

Sparse Assign: **2600:100::/28**

Search:

Filter by type: All types

3M	(Resource Holder)
543	(Resource Holder)
544	(Resource Holder)
6connect TEST	(LIR)
aaQAEntry	(Resource Holder)
aaQAEntry 2 Clone Test	(Resource Holder)
aaQAEntry4	(Resource Holder)
aaQAEntryA	(Resource Holder)
aaQAEntryA	(aaQASection)
abc	(LIR)
Advanced Turf Solutions	(Resource Holder)

Assigned to 3M successfully!

New resource

Close

The resource will be assigned according to the distribution algorithm and may be further managed in IPAM Manage for the aggregate.

Manage an Aggregate

Managing an aggregate is mostly performed in the IPAM Manage screen for the aggregate.

From IPAM Manage, you can perform the aggregate template actions of Auto-Split / Clean-Up, Set IPAM Alert information, export the block list, as well as manage individual blocks.

For detailed information on using the IPAM Manage screen and managing at a block level, see [Working with IP Blocks](#).

IPAMv2

IPAM

VLAN

Logging

Manage aggregate

16.0.0.0/12 - ARIN

Switch to Parent view

export to CSV

actions +

Search within this aggregate

clear

filter >


IT Address	IT Host	IT LIR	IT Region	IT Tags	IT Notes	IT Assigned to	IT ...	IT VLAN	IT A...	IT Updated	IT NAT	IT Meta1
16.0.0.0/14	262144	ARIN Default...	Denver, CO	Customer	-	Some Co.	-	3	8038	2019-07-30	-	-
16.4.0.0/16	65536	ARIN Default...	Denver, CO	Customer	-	available	-	3	8038	2019-07-25	-	-
16.5.0.0/22	1024	ARIN Default...	Denver, CO	Customer	-	available	-	3	8038	2019-07-30	-	-
16.5.4.0/22	1024	ARIN Default...	Denver, CO	Customer	-	available	-	3	8038	2019-07-30	-	-
16.5.8.0/21	2048	ARIN Default...	Denver, CO	Customer,Generic Tag	Some Note	A Customer	-	-	8038	2019-07-30	-	Some Inf...
16.5.16.0/20	4096	ARIN Default...	Denver, CO	Customer,Generic Tag	Some Note	A Customer	-	-	8038	2019-07-30	-	Some Inf...
16.5.32.0/19	8192	ARIN Default...	Denver, CO	Customer	Some Note	available	-	-	8038	2019-07-25	-	Some Inf...
16.5.64.0/18	16384	ARIN Default...	Denver, CO	Customer	Some Note	available	-	-	8038	2019-07-25	-	Some Inf...
16.5.128.0/17	32768	ARIN Default...	Denver, CO	Customer	Some Note	available	-	-	8038	2019-07-25	-	Some Inf...
16.6.0.0/15	131072	ARIN Default...	Denver, CO	Customer	Some Note	available	-	-	8038	2019-07-25	-	Some Inf...
16.8.0.0/13	524288	ARIN Default...	Denver, CO	Customer	Some Note	available	-	-	8038	2019-07-30	-	Some Inf...

Displaying 1 to 11 of 11 blocks


Open IPAM Manage for an Aggregate

Open the IPAM Manage screen for a block by:


- Searching for the block in the Global search, and clicking on the resulting CIDR
- Clicking the "Open" link in the aggregate blocks list from the **IPAM** tab.



- Clicking on the CIDR header of the Aggregate Block Host Utilization module, or selecting "Edit" from the module's Gear Icon from the **IPAM** tab.



- Clicking on the CIDR listed in the Aggregate Info box in IPAM Maps



Aggregate Actions

Open up aggregate level actions in IPAM Manage by clicking on the "Actions" link in the Manage Aggregate header.

Three options are available - Auto Split, Clean Up, and Manage Alerts.

Manage aggregate

16.0.0.0/8 - ARIN

Switch to Parent view

export to CSV

actions -

Search within this aggregate

clear

filter >

Auto Split

Automatically split block into sub-blocks of a specified size: Specifying a limit will split only the specified number blocks of selected size from the aggregate.

Size: Limit:

* The provided limit must always be a power of 2 (2,4,8,...).

Split

Clean Up

Clean up split blocks into larger block of size:

Block contains 103 assignment/s. Aggregating block may remove some or all of these assignments.

☐ Ignore assignments when cleaning up?

Clean up

Manage Alerts

Send an alert email when available space for falls below a specified level.

Email to:

Level (%):

clear Save alert

IT Address	IT Hosts	IT ASN	IT Region	IT Notes	IT Tags	IT Assigned to	IT Generi...	IT VLAN	IT Updated	IT NA
16.0.0.0/14	-	-	-	QA3		available	-	-	2019-07-19	-
16.4.0.0/16	-	-	-	QA3		123 Departme...	-	-	2019-07-17	-
16.5.0.0/23	-	-	-	QA3		123 Departme...	-	-	2019-07-17	-

Auto Split Aggregate

Auto Split an available aggregate into blocks of a specific size, up to a specific quantity of blocks by selecting "Size" and "Limit" under "Auto Split".

The block limit must be a power of two, or an error will appear. When done, click "Split".

Manage aggregate

5.5.5.0/24 - ARIN Switch to Parent view export to CSV actions - Search within this aggregate Q clear filter >

Auto Split

Automatically split block into sub-blocks of a specified size: Specifying a limit will split only the specified number blocks of selected size from the aggregate.

Size: /27 Limit: 8

* The provided limit must always be a power of 2 (2,4,8,...).

Split

Clean Up

Clean up split blocks into larger block of size: Clean up

Manage Alerts

Send an alert email when available space for falls below a specified level.

Email to: Level (%): clear Save alert

IT Address	IT Hosts	IT ASN	IT Region	IT Notes	IT Tags	IT Assigned to	IT Generi...	IT VLAN	IT Updated	IT NA
5.5.5.0/24	-	-	Miami, FL	-	QA	A Customer →	-	QA VLA...	2019-07-19	-

Clean Up Aggregate

Clean up an Aggregate into fewer blocks of a specific size, by selecting your desired block size and clicking "ignore assignments" (if blocks have assignments that would prevent merging).

When done, click the "Clean Up" button. All blocks will be merged to the set size and reset to available.

Manage aggregate

16.0.0.0/8 - ARIN Switch to Parent view export to CSV actions - Search within this aggregate Q clear filter >

Auto Split

Automatically split block into sub-blocks of a specified size: Specifying a limit will split only the specified number blocks of selected size from the aggregate.

Size: Limit: Split

* The provided limit must always be a power of 2 (2,4,8,...).

Clean Up

Clean up split blocks into larger block of size: /24

Block contains 103 assignment/s. Aggregating block may remove some or all of these assignments.

☒ Ignore assignments when cleaning up? **Clean up**

Manage Alerts

Send an alert email when available space for falls below a specified level.

Email to: Level (%): clear Save alert

Set Aggregate Alerts

Enable or clear aggregate alert emails for the aggregate by setting an email address and utilization percentage level.

When the aggregate is utilized to the set percent, an email alert will be sent to the provided address.



Note: the "IPAM Alerts" task must be created and set to the desired notification frequency in the [Admin Scheduler Tab](#) in order for the emails to be sent.

Manage aggregate

5.5.5.0/24 - ARIN Switch to Parent view export to CSV actions - Search within this aggregate Q clear filter >

Auto Split

Automatically split block into sub-blocks of a specified size: Specifying a limit will split only the specified number blocks of selected size from the aggregate.

Size: Limit:

* The provided limit must always be a power of 2 (2,4,8,...).

Split

Clean Up

Clean up split blocks into larger block of size:

Clean up

Manage Alerts

Send an alert email when available space for falls below a specified level.

Email to:

Level (%):

clear Save alert

When done, click "Save Alert". To clear an existing alert, hit "Clear Alert", and the alert information will be removed and status saved.

Working with IP Blocks

For additional information on performing IPAM tasks and working with blocks, continue on to [Working with IP Blocks](#).

Additional Information

For additional information on working with the IPAM system in ProVision, see the following areas:

- [IPAM Tab](#)
- [Gadgets \(IPAM and IPAMv2 Gadgets\)](#)
- [Working with IP Rules](#)
- [IPAM Administration](#)