

Working with DNS Servers

DNS Servers

DNSv3 combines server management, group organization, and zone management under the **DNS** tab.

The screenshot shows the DNSv3 interface with a navigation bar at the top containing 'Dashboard', 'Resources', 'DNS', 'DHCP', 'Servers', 'IPAM', 'Peering', 'Reporting', and 'Global Commander'. A search bar is on the right. Below the navigation bar, there are tabs for 'DNSv3', 'DNS Groups', 'DNS Servers', 'DNS Zones', and 'DNS Records'. The 'DNS Servers' tab is selected, and an 'Add Server' button is visible. The main content area is titled 'DNS Server List' and contains a table with the following data:

Server Name	Server Backend	Server Type	Server Status	Actions
BIND DNS QA Server	ISCBIND	master		Delete Push Perms
RHEL8 6cDNS Server Managed DNS	PVDNS	master	->Pending changes !	Delete Push Perms
Test Server 1	ISCBIND	master		Delete Push Perms
Fake S64 Server 1	SECURE64X86	master		Delete Push Perms
Approvals Test Server	ISCBIND	master		Delete Push Perms
Ubuntu DNS Managed DNS	PVDNS	master		Delete Push Perms

At the bottom of the table, there is a pagination control: 'Page : < 1 > Go'.

The **DNS Servers** tab is viewable by users with Resource read permissions, though only Admin users or those specifically granted server permissions may perform management actions. The Sever List contains functions for adding, updating, and managing DNS servers as well as scheduling server tasks.

- DNS Servers
 - DNS Server List Interface
- Working with DNS Servers
 - Add a Server
 - Server Settings
 - 1) Set Server Common Settings
 - 2) Set Server Specific Settings
 - Test Connection (Optional)
 - 3) Set DNS Group Settings for Server
 - 4) Save Changes
 - Edit Servers
 - Review Zones Connected to a Server
 - Zones Directly Connected to the Server
 - Zones Connected via a Group
 - Pushing a Server
 - Manual Push
 - Scheduled Push
 - Delete a Server
- Additional Information

DNS Server List Interface

DNSv3
DNS Groups
DNS Servers
DNS Zones
DNS Records
Add Server

DNS Server List

Server Name	Server Backend	Server Type	Server Status	Actions
BIND DNS QA Server	ISCBIND	master		Delete Push Perms
RHEL8 6cDNS Server Managed DNS	PVDNS	master	->Pending changes !	Delete Push Perms
Test Server 1	ISCBIND	master		Delete Push Perms
Fake S64 Server 1	SECURE64X86	master		Delete Push Perms
Approvals Test Server	ISCBIND	master		Delete Push Perms
Ubuntu DNS Managed DNS	PVDNS	master		Delete Push Perms

Page :
« 1 »
Go

1) **Add Server Button:** Opens a dialog for creating a DNS server.

2) **Server List:**

3) **Server Name:** Name of the DNS server. Click to open server details.

4) **Server Backend:** The DNS Service backend type for the server.

5) **Server Type:** Whether the server is a master or slave type.

6) **Server Status:** Display of server error and connection status messages.

7) **Actions:** The actions that may be performed on each server:

Actions

Delete Push Perms

8) **Delete:** Deletes the server from ProVision.

9) **Push:** Pushes all zones associated with the selected server.

10) **Perms:** Opens a shortcut to edit permissions for the selected server (Admin only).

Working with DNS Servers

Add a Server

To create a new server, start from the [DNS](#) Tab, select the **DNS Servers** sub menu. Then, click the "Add Server" button next to "DNS Server List".

DNSv3
DNS Groups
DNS Servers
DNS Zones
DNS Records
Add Server

DNS Server List

Server Name	Server Backend	Server Type	Server Status	Actions
BIND DNS QA Server	ISCBIND	master		Delete Push Perms

This will open the "Server Settings" page.

Server Settings

1) Set Server Common Settings

In the "Common Settings" section of Server Settings, enter the new server's Display Name (the name that will appear on the ProVision interface), the FQDN / IP, server type, service type, and desired parent Resource (may be left at the default Top Level Resource).

Server Settings :

Edit the comment.

Common Settings

Display Name:

This is the server name that will appear in the DNS interface.

FQDN or IP:

The IP address that ProVision will use to connect to this server.

DNS Port:

The port will be used for DDNS and DNS Queries to the server.

Server Type:

Master

Export Zones:

ON

DNS Service:

ISC BIND

Parent Resource:

TLR

The new server resource will be a child of the Parent Resource.

Enable Records Check:

ON

ProVision is checking if the DNS responds with a proper values to the zone records. In order record monitoring to work properly, you must enter a proper NameServer as "FQDN or IP" field.

Enable TSIG Key for transfers:

OFF

If enabled, the provided TSIG key will be added to the ACL config of the related DNS Servers.

Display Name: Name you want the server to display.

FQDN or IP: The FQDN or ip address of the DNS server.

DNS Port: Specify a DNS Port.

Server Type: Specify if the server is a master or slave. Different configuration files are created master vs. slave on the Bind, PowerDNS /Bind, and Secure64 platforms.

Export Zones: Enable / Disable Zone export

DNS Service: Select the DNS service type (ISC Bind, Secure64, KnotDNS, etc).

Parent Resource: Select the resource to be the "parent" of the server - typically TLR (Top Level Resource), but may be a lower level resource such as a Customer or Location. The parent resource selection is the basis of access permissions for the server.

Enable Records Check: Enable / Disable zone record checks.

Enable TSIG Key for transfers: Enable / Disable TSIG Keys. If enabled, the provided key will be added to the ACL config for the server (s).

2) Set Server Specific Settings

The next section is entering server service-type specific settings. The options visible in this section will depend on the "DNS Service" type chosen under "Common Settings".

Here, we see the fields for ISC BIND server settings. Enter the server Username, Password, Port, Remote Director, Named Conf. Path, and Pre /Post Command (if desired). Your fields may vary for other server types.

For SSH Public Key Authentication, DNSSEC, and Dynamic Option updates, click on the ON / OFF toggle to select "ON" or "OFF" for each as needed.

ISC BIND Settings

SSH Public Key Authentication:

OFF

Please choose your SSH authentication type.

Username:

Enter Username

Username for the SSH connection. It must have write access to the Bind configurations and zone folders. Bind must also have write permissions to the files that are created with the user.

Password:

Enter Password

Port:

22

Server SSH Port.

SSH Route:

Use ssh routes in order to define a chain from ssh jump hosts.

Remote Directory:

/etc/bind/zones

Path to the remote server where to store the generated zone files.

Named Conf Path:

/etc/bind/_named.conf

Path to the named.conf config.

Zones Relative Path (chroot environment):

ex: /zones/

This path will be used to configure where the zone files are stored relative to the named root. This must be configured properly if you are running ISC BIND with the chroot isolation flag.

Public IP Address:

123.123.123.123

The public-facing IP address for this server used in writing server configs. If omitted, the 'FQDN or IP' field will be used.

Notify IP Address:

123.123.123.123

The IP Address will be used into the allow-notify section of the slaves that has this server as a master.

Pre Command:

Post Command:

ex: service bind9 reload

Enable DNSSEC:

ON

Enable Dynamic Updates:

ON

Catalog Zones settings

Enable Catalog Zone:

OFF

By enabling Catalog Zone all the zones inside the group will be exported into a new catalog zone, so the slave servers can receive the zone changes.

SSH Public Key Authentication: If applicable, toggle "On" or "Off"

Username: Login/username for the target DNS server. The specified account needs to be valid, and have write permission to the remote directory and execute permission for any pre/post commands.

Password: Password for the target account. All passwords are stored encrypted in the database.

Port: Port to contact the target server on. This is port used for SSH on Bind and Secure64 server types.

Remote Directory: The target directory to transfer zone files to on the DNS system.

Named Conf Path: The path to other zones on the Bind systems.

Pre Command: Any valid system command on the target DNS system. This command will be run before any files are transferred.

Post Command: Any valid system command on the target DNS system. This command will be run after any files are transferred. For example, on a Bind system you would need to run "rndc reload" to reload the zones.

Enable DNSSEC: If available for the server type, toggle to "On" or "Off". See Configuring DNSSEC for additional information.

Enable Dynamic Updates: Toggle to "On" or "Off", if the server allows dynamic updates. Records will then be pushed to zone files using REST API dynamically whenever any modifications are made, i.e. record creation/deletion.

Catalog Zone Settings: Opt to enable / disable catalog zones for the server.

Some DNS Server types use subscription services or outside accounts, in which case you may instead be prompted to provide account credentials, API keys, API secret, or other vendor-specific fields to connect to the service.

Test Connection (Optional)

After entering the server-specific settings in this section, you may click the "Test Connection" button at the bottom right of the page to test the server connection and authentication.


The "Test Connection" button will attempt to login to the target system and write to the target directory.



A window will pop up showing a success or failure response.

If any failures are encountered, an error will be written with some detail.

If the test is successful, the word "Success!" will show verifying that files can be transferred. This does not test if the user can execute pre/post commands. This needs to be checked manually.



3) Set DNS Group Settings for Server

In the last section, select whether to enable Multiple Groups Support for exporting Groups as View (click to toggles ON / OFF), and select a default Group, if desired, to be associated with the server. Zones assigned to the selected Group will automatically be attached to the server.

DNS Group Settings

Multiple Groups Support:

ON

Check this option if you want to enable the support of different DNS Groups to be exported as Views. **Danger !** In case the server doesn't support Views you must take care to not have duplicated zone names in the groups !

Export Groups as Views:

ON

If this option is checked the Groups will be exported as Views on push. (It works only on servers that support Views like ISC BIND)!

Default Group for Direct Zones:

Default Group

The zones that are directly connected to the server are going to added to this group.

Attach to Groups:

× Default Group

× Example Group

× New Test Group

The server will be attached to the list of the groups and the zones from the groups are going to be exported automatically.

4) Save Changes

Save your changes when done! Just click the "Save Changes" button at the bottom right of the page.

DNS Group Settings

Multiple Groups Support:

OFF

Check this option if you want to enable the support of different DNS Groups to be exported as Views. **Danger !** In case the server doesn't support Views you must take care to not have duplicated zone names in the groups !

Export Groups as Views:

OFF

If this option is checked the Groups will be exported as Views on push. (It works only on servers that support Views like ISC BIND)!

Attach to Group:

No Default Group

If you select a default DNS group to your server, the zones assigned to this group will be automatically attached to the server.

Test Connection

Save changes

The new server will now be added to the DNS Servers list. These settings may be changed at any time by selecting the server from the server list and editing the information.

Edit Servers

Edit an existing server by clicking once on the server name in the DNS Servers list.

Example server	ISCBIND	master	Delete	Push
----------------	---------	--------	--------	------

The "Server Settings" page will open.

Server Settings : Example Server

Push ZonesSchedule PushImport Zones

Edit the comment.

Common Settings

Display Name:

Example Server

This is the server name that will appear in the DNS interface.

FQDN or IP:

ns1.dns.example.com

The IP address that ProVision will use to connect to this server.

Server Type:

Master

Export Zones:

OFF

DNS Service:

ISC BIND

Parent Resource:

TLR

The new server resource will be a child of the Parent Resource.

Enable Records Check:

ON

ProVision is checking if the DNS responds with a proper values to the zone records. In order record monitoring to work properly, you must enter a proper NameServer as "FQDN or IP" field.

Click inside the field that you want to change, type your changes, and then click "Save Changes" at the bottom of the page.

DNS Group Settings

Multiple Groups Support:

OFF

Check this option if you want to enable the support of different DNS Groups to be exported as Views. **Danger !** In case the server doesn't support Views you must take care to not have duplicated zone names in the groups !

Export Groups as Views:

OFF

If this option is checked the Groups will be exported as Views on push. (It works only on servers that support Views like ISC BIND)!

Attach to Group:

No Default Group

If you select a default DNS group to your server, the zones assigned to this group will be automatically attached to the server.

Test ConnectionSave changes

Review Zones Connected to a Server

There are two ways that zones may be connected to a DNS server:

1) Directly connected, by attaching the zone to a server from the View Zone page.

or,

2) Connected by a Group that has been set as the default DNS Group for the server, selected under "DNS Group Settings".

Both are able to be viewed on the DNS Server Settings page.

To view either, open the Server Settings page for the server by clicking on the server name in the DNS Servers list.

Edit an existing server by clicking once on the server name in the DNS Servers list.

The "Server Settings" page will open.

Zones Directly Connected to the Server

Scroll to the bottom of the page, and open the module titled "Zones directly connected to the server" by clicking on the expansion arrow.

Zones directly connected to the server

A zone list will show the zone(s) that have been directly connected to this server.

Here, you may browse through forward and reverse zones by selecting the "Forward Zones" or "Reverse Zones" tabs, sort the list by Zone Name or Last Modified, open the zone's page by clicking on the name, or check the zone's status by clicking the "Check" button.

Zones directly connected to the server

Export Zones

Forward Zones

Reverse Zones

Zone Name	Last Pushed	Last Modified	Records	Zone Status	Actions
ibmZoneUpdateTest2.com.	05/10/2017 12:53:39	06/05/2017 14:42:32	0	Contains Errors	Check

Zones may be exported by clicking the "Export Zones" button.

Zones Connected via a Group

If a default Group has been selected under "DNS Group Settings" for the server, Zones under that Group will be connected to the server and able to be viewed on the Server Settings page.

Scroll to the bottom of the page, and open the module titled "Zones connected to Group '(Group Name)' " by clicking on the expansion arrow.

DNS Group Settings

Multiple Groups Support:

OFF

Check this option if you want to enable the support of different DNS Groups to be exported as Views. **Danger !** In case the server doesn't support Views you must take care to not have duplicated zone names in the groups !

Export Groups as Views:

OFF

If this option is checked the Groups will be exported as Views on push. (It works only on servers that support Views like ISC BIND)!

Attach to Group:

Default Group

If you select a default DNS group to your server, the zones assigned to this group will be automatically attached to the server.

Test Connection

Save changes

Zones connected to Group: "Default Group"

A zone list will show the zone(s) that connected to this server via a selected Group.

Here, you may browse through forward and reverse zones in that Group by selecting the "Forward Zones" or "Reverse Zones" tabs, sort the list by Zone Name or Last Modified, open the zone's page by clicking on the name, or check the zone's status by clicking the "Check" button.

Zones connected to Group: "DNS Group 1"					
Forward Zones		Reverse Zones			
Zone Name	Last Pushed	Last Modified	Records	Zone Status	Actions
msn.com.		02/24/2017 14:02:27	6		Check
msn2.com.		03/27/2017 14:21:58	4		Check

Pushing a Server

Manual Push

Manually pushing all zones on a server may be done directly from the DNS Server list. Under the "Actions" section of the Server List, click the "Push" button for the desired server.

ANewServer	ISCBIND	master	Delete Push Perms
------------	---------	--------	---

Pushing may also be done while in the Server Settings page. While in the Server Settings page, click the "Push Zones" button at the top right of the page.

DNSv3
DNS Groups
DNS Servers
DNS Zones
DNS Records

Server Settings : Example Server
[Push Zones](#)
[Schedule Push](#)
[Import Zones](#)

Edit the comment.

Common Settings

Users can customize a push by choosing an option from the push options modal and clicking "Execute Push". To push normally, click "Execute Push" without selecting any options.

DNS Push Options


☐ Push Modified Zones Only
Push only the zones that have been modified since the last push.

☐ Push to Masters Only
If this option is checked, the Push request will be executed only to Master Servers.

☐ Push Config Only
Push only zone config declarations. WARNING If you have zones that have never been pushed, you may end up with a config declaration and a missing zone file.

[Execute Push](#)
[Close](#)

A "DNS Push Status" box will appear, showing the status of each zone as it is pushed. Once all zones have been pushed successfully, a green status message of "Finished DNS Pushing Request" will appear. At this point, the push is complete and the window may be closed.




Scheduled Push

DNS server pushes may be scheduled from either the Admin Area [Scheduler](#) Tab, or from within the DNSv3 Server Settings page. Scheduled pushes require Admin access.

For information on scheduling a push from the [Scheduler](#) Tab, see [Scheduler Tab](#) documentation.

To schedule a push from a server's Settings page, open the Server Settings page for the desired server, and click on the "Schedule Push" button.



The Push Scheduler dialog will open. Click on the calendar on the left to select a date for the push, set the desired push time on the right, enter a notification email address, and then click "Save Changes".

Push Scheduler

Pick date and time (UTC):

<

January 2022

>

Su

Mo

Tu

We

Th

Fr

Sa

26

27

28

29

30

31

1

2

3

4

5

6

7

8

9

10

11

12

13

14

15

16

17

18

19

20

21

22

23

24

25

26

27

28

29

30

31

1

2

3

4

5

Time

19:28

19:29

19:30

19:31

19:32

19:33

19:34

Notification Email:


something@example.com

Close

Save changes

Once a schedule push has been created, a "Scheduled Tasks" module will appear at the top of the Server Settings page.

Click on the expansion arrow for the module to open and view the tasks.



Scheduled pushes for the server will be listed in the "Scheduled Tasks" module, and may be viewed or deleted (by clicking the "Delete" button under "Actions").

Server Settings : Example Server			
Scheduled Tasks			
Task Name	Last Run	Repeat Time	Actions
DNS Server Scheduled Push: Example server	2021-11-20 02:35:01 UTC	20th of every month at 02:35 UTC	Delete

If necessary, the Scheduled Push may be edited from the [Scheduler](#) Tab in the Admin area. See the [Scheduler Tab](#) for information on editing scheduled tasks.

Delete a Server

Delete a server by clicking the "Delete" button under the "Actions" section of the Server List for the desired server.

Additional Information

For additional information on working in DNS, see the following sections:

- [Configuring ISC BIND Support](#)
- [Configuring PowerDNS Support](#)
- [Configuring Secure64 Support](#)
- [Configuring Split Horizon and Views](#)
- [Configuring DNSSEC](#)
- [Import DNS Zones](#)
- [DNS Tab](#)