Configuring PowerDNS Support

Configuring PowerDNS Support

- Configuring PowerDNS Support
 - Environments supported
 - Step 1: Add a PowerDNS Server
 - Server Settings
 - 1) Set Server Common Settings
 - 2) Set Server Specific Settings
 - 3) Set DNS Group Settings for Server
 - 4) Save Changes
 - Step 2: Import PowerDNS Zones
 - Step 3: Push zones to PowerDNS
 - BIND Backend
 - MySQL Backend
- Additional Information

Environments supported

- PowerDNS version 3.0 or above on the target server(s)
- BIND or MySQL backend

Step 1: Add a PowerDNS Server

To create a new server, start from the DNS Tab, select the DNS Servers sub menu. Then, click the "Add Server" button next to "DNS Server List".

DNSv3	DNS Groups	DNS Servers	DNS Zones		
DNS Server List Add Server					
DING Server List					

This will open the "Server Settings" page.

Server Settings

1) Set Server Common Settings

In the "Common Settings" section of Server Settings, enter the new server's Display Name (the name that will appear on the ProVision interface), the FQDN / IP, server type, DNS service type, and desired parent Resource (may be left at the default Top Level Resource). For PowerDNS servers, ensure that either "PowerDNS BIND" or "PowerDNS MySQL" is selected under DSN server type.

Display Name:			
Enter Display Name			
This is the server name that will appear in the	DNS interface.		
FQDN or IP:			
ex: ns1.dns.6connect.net or 216.239.32.10			
DNS server real FQDN or IP Address.			
Server Type:			
Master			
DNS Service:			
PowerDNS Bind			
Parent Resource:			
TID			

2) Set Server Specific Settings

The next section is entering server service-type specific settings. The options visible in this section will depend on the "DNS Service" type chosen under "Common Settings".

Here, we see the fields for PowerDNS BIND server settings. Enter the server Username, Password, Port, Remote Director, Named Conf. Path, and Pre/Post Command (if desired). Your fields may vary for other server types.

For SSH Public Key Authentication, DNSSEC, and Dynamic Option updates, click on the ON / OFF toggle to select "ON" or "OFF" for each as needed.

SS	SH Public Key Authentication:
Ple	ease choose your SSH authentication type.
Us	sername:
	Enter Username
Us tha	sername for the SSH connection. It must have write access to the PowerDNS configurations and zone folders. PowerDNS must also have write permissions to the file at are created with the user.
Pa	assword:
	Enter Password
Po	ort:
	22
Se	arver SSH Port.
Re	emote Directory:
	/etc/powerdns/6c-zones
Pa	th to the remote server where to store the generated zone files.
Na	amed Conf Path:
	/etc/powerdns/6connect_named.conf
Pa	th to the named.conf config.
Pr	e Command:
Po	bst Command:
	ex: pdns_control rediscover
En	nable DNSSEC: ON O
En	nable Dynamic Updates:
In	order to support Dynamic DNS Update you must have PowerDNS version 3.4.0 or bigger. You must set "allow-dnsupdate-from=Provision IP" and "dnsupdate=ves" of

After entering the server-specific settings in this section, you can click the "Test Server" button at the top of the section to test the server connection and authentication.



A window will pop up showing a success or failure response.

DNS Server Status	×
Success!	
	Close

3) Set DNS Group Settings for Server

In the last section, select a default Group to be associated with the server. Zones assigned to the selected Group will automatically be attached to the server.

tach to Group:		
DNS Group 1		(\$
you select a default DNS group to you	r server, the zones assigned to this group will be automatically attached to the server.	

4) Save Changes

Save your changes when done! Just click the "Save Changes" button at the bottom right of the page.

tach to Group:				
DNS Group 1				÷
you select a default DNS group to yo	ur server, the zones assigned to this	s group will be automatically at	tached to the server.	

The new server will now be added to the DNS Servers list. These settings may be changed at any time by selecting the server from the server list and editing the information.

Step 2: Import PowerDNS Zones

While in the Admin section, navigate to the Data Import Tab. Select the "Power DNS Zone Import" link.

To import your data, simply choose your PowerDNS server and click "Import".

This operation will pull all zones on the target server.				
This operation may take quite some time.				
Choose a server:				
Import				

Step 3: Push zones to PowerDNS

Navigate back to the DNS tab, and select the "DNS Servers" tab.

Locate the PowerDNS server in the DNS Servers list, and then click the "Push" button under "Actions" at the end of the row.

ANewServer	ISCBIND	master	Delete Push Perms

BIND Backend

Note on SSH

The integration does not require a remote database connection, but it does require an SSH account and a writable directory. The SSH account must have access to the server. This account will also be used for DNSSEC functionality within PowerDNS.

MySQL Backend

Note on SSH

The integration requires a remote database connection, so will need a mysql user with permissions for remote administration. We highly recommend using ACLs to ensure that configuration only occurs from intended sources.

For DNSSEC functionality, you will need a standard SSH user account withing your PowerDNS user group

Please note that Views are not supported with the MySQL backend

Only BIND and MySQL backends are supported.

Additional Information

For additional information on working in DNS, see the following sections:

- · Working with DNS Servers
- Configuring ISC BIND Support
- Configuring Secure64 Support
- Configuring Split Horizon/Views
- Configuring DNSSEC
- Import DNS Zones
- DNS Tab