Working with DHCP Servers

DHCP Servers

The DHCP tab combines server management, group organization, and pool management together under a single tab.

	Resources - DNS -	DHCP - Servers IPAM - P	eering 👻 Reporting 👻 Global Commar	nder -	Search
DHCP	DHCP Groups	DHCP Servers DHCP Poo	DHCP Classes DHCP Lo	ogging	Add Server
DHCF	P Server L	ist			
Server N	ame	Server Backend	Server Host	Parent Resource	Actions
		control Duchtonia		T di chi ti toccui co	,
QA DHCF	P VM	ISC	test-tools.6clabs.com	TLR	Delete Push Perms
QA DHCF	• VM er 1	ISC	test-tools.6clabs.com	TLR QA Test Resource 2	Delete Push Perms Delete Push Perms
QA DHCF Test Serve Approvals	2 VM er 1 5 Test Server	ISC ISC ISC	test-tools.6clabs.com test.com test.com	TLR QA Test Resource 2 TLR	Delete Push Perms Delete Push Perms Delete Push Perms

The DHCP Servers tab contains functions for adding, updating, and managing DHCP servers as well as scheduling server tasks.

Users with resource "read" permissions may view DHCP Server information, however only those with either Admin permissions or granted grouplevel server permissions can manage DHCP server creation, edits, and deletion.

- DHCP Servers
 - DHCP Server List Interface
- Working with DHCP Servers
 - Add a Server
 - Server Settings
 - 1) Set Server Common Settings
 - 2) Set Server Specific Settings
 - 3) Set Advanced Server Settings
 - 4) Set DHCP Group Settings for Server
 - 5) Save Changes
 - Edit Servers
 - Review Pools Connected to a Server
 - Pools Directly Connected to the Server
 - Zones Connected via a Group
 - Pushing a Server
 - Manual Push
 - Scheduled Push
 - Review Pushed / Unpushed Configurations
 - Scan a Server
 - Delete a Server
- Additional Information

DHCP Server List Interface

DHCP DHCP Groups DHCP S	ervers DHCP Pools	DHCP Classes DHCP Loggin	g	Add Server
DHCP Server List				
Server Name	Server Backend	Server Host	Parent Resource	Actions
QA DHCP VM	ISC	test-tools.6clabs.com	TLR	Delete Push Perms
Test Server 1	ISC	test.com	QA Test Resource 2	Delete Push Perms
Approvals Test Server	ISC	test.com	TLR	Delete Push Perms
Centos DHCP Managed DHCP	PVDHCPMYSQL	empty-centos1.6clabs.com	Centos DHCP	Delete Push Perms

- 1) Add Server Button: Opens a dialog for creating a DHCP server.
- 2) Server List:
 - 3) Server Name: Name of the DHCP server. Click to open server details.
 - 4) Server Backend: The DHCP Service backend type for the server. Available types are ISC and CPNR.
 - 5) Server Host: The server host.
 - 6) Parent Resource: The resource set as the Parent for the server.
 - 7) Actions: The actions that may be performed on each server:

Actions		
Delete	Push	Perms

8) Delete: Deletes the server from ProVision.

9) Push: Pushes all pools associated with the selected server.

10) Perms: Opens a shortcut to edit permissions for the selected server (Admin only).

Working with DHCP Servers

Add a Server

To create a new server, start from the DHCP Tab, select the DHCP Servers sub menu. Then, click the "Add Server" button next to "DHCP Server List".

DHCP DHCP Groups	DHCP Servers DHCP Pools	DHCP Classes DHCP Lo	ogging	Add Server
DHCP Server L	_ist			
DHCP Server L	List Server Backend	Server Host	Parent Resource	Actions

This will open the "Server Settings" page.

Server Settings

1) Set Server Common Settings

In the "Common Settings" section of Server Settings, enter the new server's Display Name (the name that will appear on the ProVision interface), the FQDN / IP, server type, service type, and desired parent Resource (may be left at the default Top Level Resource).

Common Settings	
Display Name:	
Enter Display Name	
This is the server name that will appear in the DHCP interface.	
Server IP:	
ex: 216.239.32.10	
DHCP server IP or Hostname.	
DHCP Service:	
ISC DHCP	
Parent Resource:	
TLR	

Display Name: Name you want the server to display.

Server IP: The IP or Hostname of the DHCP server.

DHCP Service: Select the DHCP service type - ISC DHCP, or Cisco Prime Network Registrar (CPNR).

Parent Resource: Select the resource to be the "parent" of the server - typically TLR (Top Level Resource), but may be a lower level resource such as a Customer or Location. The parent resource selection is the basis of access permissions for the server.

2) Set Server Specific Settings

The next section is entering server service-type specific settings. The options visible in this section will depend on the "DHCP Service" type chosen under "Common Settings".

Here, we see the fields for ISC DHCP server settings. Enter the server Username, Password, Port, Leases Directory, Server Start / Stop Commands, Server Test Command and Freelines (if desired).

Your fields may vary for other server types.

For SSH Public Key Authentication, click on the ON / OFF toggle to select "ON" or "OFF" as needed.

ISC DHCP Connection Settings	
SSH Public Key Authentication:	OFF
Please choose your SSH authentication	type.
Username:	
Enter Username	
Username for the SSH connection. It m	ust have write access to the ISC DHCP configurations.
Password:	
Enter Password	
Port:	
22	
Server SSH Port.	
SSH Route:	
	x *
Use ssh routes in order to define a chai	n from ssh jump hosts.
Config File Path:	
/etc/dhcp/dhcpd.conf	
Path to the dhcpd.conf config.	
Leases Directory:	
/var/lib/dhcp	
Path to the remote server where the lea	ises are located.
Server Type:	
DHCPv4	· · · · · · · · · · · · · · · · · · ·
Depending on the Server type with opti-	on -4 or -6 ProVision will export only IPv4 or IPv6 pools.
Server Start Command:	
/etc/init.d/dhcpd start	
Server Stop Command:	
/etc/init.d/dhcpd stop	
Config Test Command:	
/etc/init.d/dhcpd configtest	
Skip Config Test:	(O OFF)
If set to On, Config Test command will r	to be executed on the generated dhcpd.conf .
Skip PID Check:	OFF
If set to On, checking for new dhcpd pic	l will be disabled.
Freelines:	
The Freelines will be applied to the serv	/er configuration.

3) Set Advanced Server Settings

If desired, Advanced Settings for the DHCP Server may be entered. Toggle "Authoritative Server" to "On" or "Off", and fill in the fields for Routers, Domain Name Servers, Domain Name, Default Lease Time, Max Lease Time, Local Port, or Log Facility.

Authoritative Server:	OFF		
Routers:			
Enter Routers.			
Domain Name Servers:			
Enter Domain Name Servers.			
Domain Name:			
Enter Domain Name.			
Default Lease Time:			
Ex 600			
Max Lease Time:			
Ex. 86400			
Local Port:			
Ex. 67			
Log Facility:			

After entering the server-specific settings in this section, you can click the "Test Connection" button at the bottom right of the page to test the server connection and authentication.

Test Connection	Save changes		
A success or failure response will pop up.			
		Test Connection	Save chang
Successfully connected.			

4) Set DHCP Group Settings for Server

In the last section, select whether to attach the server to an existing DHCP Group. Pools assigned to the selected Group will automatically be attached to the server.

DHCP Group Settings	
Attach to Groups:	
× Test Group	
The server will be attached to the list of the groups and the pools from the groups are going to be exported automatically.	

5) Save Changes

Save your changes when done! Just click the "Save Changes" button at the bottom right of the page.

Attach to Groups:	
× Test Group	
The server will be attached	to the list of the groups and the pools from the groups are going to be exported automatically.

The new server will now be added to the DHCP Servers list. These settings may be changed at any time by selecting the server from the server list and editing the information.

Edit Servers

Edit an existing server by clicking once on the server name in the DHCP Servers list.

Server Name	Server Backend	Server Host	Parent Resource	Actions
QA DHCP VM	ISC	test-tools.com	QA Test Resource	Delete Push Perms
Example DHCP Server	ISC	216.239.32.10	TLR	Delete Push Perms
50281 DHCP Module	ISC	1.2.3.4	MyNewEntry	Delete Push Perms

The "Server Settings" page will open.

Click inside the field that you want to change, type your changes, and then click "Save Changes" at the bottom of the page.

Attach to Groups:					
× Test Group					
he server will be attached to the	ist of the groups and the pools from	m the groups are going to	be exported automaticall	y.	

Review Pools Connected to a Server

There are two ways that pools may be connected to a DHCP server:

1) Directly connected, by attaching the pool to a server from the Pool Details page.

or,

2) Connected by a Group that has been set as the default DHCP Group for the server, selected under "DHCP Group Settings".

Both are able to be viewed on the DHCP Server Settings page.

To view either, open the Server Settings page for the server by clicking on the server name in the DHCP Servers list.

Edit an existing server by clicking once on the server name in the DHCP Servers list.

Server Name	Server Backend	Server Host	Parent Resource	Actions
QA DHCP VM	ISC	test-tools.com	QA Test Resource	Delete Push Perms
Example DHCP Server	ISC	216.239.32.10	TLR	Delete Push Perms
50281 DHCP Module	ISC	1.2.3.4	MyNewEntry	Delete Push Perms

The "Server Settings" page will open.

Pools Directly Connected to the Server

Scroll to the bottom of the page, and open the module titled "Pools directly connected to the server" by clicking on the expansion arrow.

ools directly co	nnected to th	e server			
Subnet Pools	Host Pools				
L ² Pool Name		↓† Last Modified	IP	MAC	Actions T
gadgethost1		12/12/2022 12:11:27	2600:450::1	00:11:22:33:44:55	Detach

A pool list will show the pool(s) that have been directly connected to this server.

Here, you may browse through subnet and host pools by selecting the appropriate tabs, sort the list by Pool Name or Last Modified, or open the Pool Details page by clicking on the name.

Zones Connected via a Group

If a default Group has been selected under "DHCP Group Settings" for the server, pools under that Group will be connected to the server and able to be viewed on the Server Settings page.

Scroll to the bottom of the page, and open the module titled "Pools connected to Group '(Group Name)' " by clicking on the expansion arrow.

Subnet Pools	Host Pools				
2 Pool Name	↓ ↑ Last Modified	Subnet	Range Min	Range Max	Actions T
Pool 1	06/23/2018 21:32:17	192.168.80.0/20	192.168.81.1	192.168.96.254	Detach
Pool 2	06/22/2018 19:31:36	10.140.93.80/30	10.140.93.81	10.140.93.82	Detach
Pool 3	06/22/2018 19:56:09	10.10.16.0/20	10.10.16.1	10.10.31.254	Detach

A pool list will show the pool(s) that have been directly connected to this server.

Here, you may browse through subnet and host pools by selecting the appropriate tabs, sort the list by Pool Name or Last Modified, or open the Pool Details page by clicking on the name.

Pushing a Server

Manual Push

Manually pushing all pools on a server may be done directly from the DHCP Server list. Under the "Actions" section of the Server List, click the "Push" button for the desired server.

Server Name	Server Backend	Server Host	Parent Resource	Actions
QA DHCP VM	ISC	test-tools.com	QA Test Resource	Delete Push Perms
Example DHCP Server	ISC	216.239.32.10	TLR	Delete Push Perms
50281 DHCP Module	ISC	1.2.3.4	MyNewEntry	Delete Push Perms

Pushing may also be done while in the Server Settings page. While in the Server Settings page, click the "Push Pool" button at the top right of the page.

DHCP DHCP Groups DHCP Servers DHCP Pools DHCP Logging		
Server Settings : DHCP - DHCP 6c Test Server - QA test	Push Pools Schedule Push	Scan Server
Unpushed Configuration		>
Current Pushed Configuration		>
Common Settings		

A "DHCP Push Status" box will appear, showing the status as the server is pushed. Once all pools have been pushed successfully, a green status message of "Finished DHCP Pushing Request" will appear. At this point, the push is complete and the window may be closed.

Scheduled Push

DHCP server pushes may be scheduled from either the Admin Area Scheduler Tab, or from within the DHCP Server Settings page. Scheduled pushes require Admin access.

For information on scheduling a push from the Scheduler Tab, see Scheduler Tab documentation.

To schedule a push from a server's Settings page, open the Server Settings page for the desired server, and click on the "Schedule Push" button.

DHCP DHCP Groups DHCP Servers DHCP Pools DHCP Logging	
Server Settings : DHCP - DHCP 6c Test Server - QA test	Push Pools Schedule Push Scan Server
Unpushed Configuration	>
Current Pushed Configuration	>
Common Settings	

The Push Scheduler dialog will open. Click on the calendar on the left to select a date for the push, set the desired push time on the right, enter a notification email address, and then click "Save Changes".

F	ous	h So	ched	uler						×
F	Pick date and time (UTC):									
		<		Jan	uary	2022		>	Time	
		Su	Мо	Tu	We	Th	Fr	Sa	19:28 🔺	
L		26	27	28	29	30	31	1	19:29	
		2	3	4	5	6	7	8	19:30	
2		9	10	11	12	13	14	15	19:31	
		16	17	18	19	20	21	22	19:32	
		23	24	25	26	27	28	29	19:33	
		30	31	1	2	3	4	5	19.34 👻	
r	Notif	icatio	on En	nail:						
	sor	nethi	ng@e	xamp	le.cor	n				
-										
								Close	Save chan	ges

Once a schedule push has been created, a "Scheduled Tasks" module will appear at the top of the Server Settings page.

Click on the expansion arrow for the module to open and view the tasks. Scheduled tasks may be deleted by clicking the "Delete" button under "Actions".

Server Settings : DHCP - DHCP 6c 1	Test Server	- QA test Push Pools	Schedule Push Scan Server
Scheduled Tasks			\sim
Task Name	Last Run	Repeat Time	Actions
Scheduled Push: DHCP - DHCP 6c Test Server - QA test		One time on 2018-06-24 at 15:20 PDT	Delete

If necessary, the Scheduled Push may be edited from the Scheduler Tab in the Admin area. See the Scheduler Tab for information on editing scheduled tasks.

Review Pushed / Unpushed Configurations

After a server has been created, unpushed edits may be viewed under the "Unpushed Configurations" module in Server Settings.

After a push, the most recent pushed configuration may be viewed under the "Current Pushed Configuration" module in Server Settings.

To open either, click the expansion arrow for the module on the top right of the header.

DHCP Groups DHCP Servers DHCP Pools DHCP Logging	
Server Settings : DHCP - DHCP 6c Test Server - QA test	Push Pools Schedule Push Scan Server
Unpushed Configuration	>
Current Pushed Configuration	(>
Common Settings	

The Unpushed Configuration module will show the edits made to the configuration since the last successful push, and the user, time, and date of the change.

erver Settings : DHCP - DHCP Test Server - QA test	Push Pools Schedule Push Scan Ser
Unpushed Configuration	>
nost HostPool { nardware ethernet 00:11:22:33:44:55; ixed-address 16.5.4.0;	
	Added by ops on 2018-06-22T17:13:09-0700
	/

In Current Pushed Configuration, you may search for a specific line by entering a term in the search bar and hitting the "Enter" key - the config will jump to the appropriate line for review.

Current Pushed Configuration	>
This is the last successfully pushed configuration. It does not reflect unpushed changes or failed pushes.	
default-lease-time 600;	
default-lease-time 600; max-lease-time 86400; local-port 67; log-facility local7;	

Scan a Server

Scan a DHCP Server by clicking the "Scan Server" button at the top of the Server Settings page.

DHCP Groups DHCP Servers DHCP Pools DHCP Logging	
Server Settings : DHCP - DHCP 6c Test Server - QA test	Push Pools Schedule Push Scan Server
Unpushed Configuration	>
Current Pushed Configuration	>
Common Settings	

When complete, a "Server Statistics" module will appear. Expand the module, and if the server permissions allow, the scanned statistics will show in the module.

If permissions or directory location fails during the scan, an error message will show instead.

Delete a Server

Delete a server by clicking the "Delete" button under the "Actions" section of the Server List for the desired server.

Server Name	Server Backend	Server Host	Parent Resource	Actions
QA DHCP VM	ISC	test-tools.com	QA Test Resource	Delete Push Perms
Example DHCP Server	ISC	216.239.32.10	TLR	Delete Push Perms
50281 DHCP Module	ISC	1.2.3.4	MyNewEntry	Delete Push Perms

Additional Information

For more information on working with DHCP, see the following areas:

- DHCP Tab
- Working with DHCP Groups
- Working with DHCP PoolsWorking with DHCP Gadgets