Configuring Split Horizon/Views

Configuring ACL Views

ProVision's ACL module applies the specified network lists to the in the named.conf for zones inside the group and the servers that belongs to the group, when exporting the group or zone.

- · Create an ACL View
- Edit an ACL
- Delete an ACL
- Add an existing ACL to another Group

Additional Information

\Lambda WARNING

If you see a view named "_6connectDefault" - DO NOT DELETE IT.

Create an ACL View

ACL views may be created under each DNS Group, accessed from the DNS tab DNS Groups sub-tab.

Expand the Group that you want the view applied to, and then expand the section "Applied ACLs" by clicking on the expansion arrow to the right of the section name.

X Example Group						~
DNS Zones	Add Zone Push Group	Schedule Push Export Zone	Perms			
Resources Await	ting Approval					>
Forward Zones	Reverse Zones					
J₂ Zone Name	Last Pushed	↓ ↑ Last Modified	Records	Zone Status	Actions T	
6connect.com.	03/13/2019 11:53:40	02/21/2019 18:30:13	2	Contains Errors	Delete Push Move Check Perms	
6connectqa.com.	02/20/2019 16:19:06	02/21/2019 18:33:56	1		Delete Push Move Check Perms	
example.com.	02/21/2019 18:26:03	02/21/2019 15:59:46	1		Delete Push Move Check Perms	
Attached Servers	S					>
Group Default Pa	arameters					>
Applied ACLs						>
Catalog Zones s	ettings					>

If ACLs already exist, they will be shown under this section.

To add a new list, click the "Add or Edit ACL" button.

Applied ACLs		×
Add or Edit ACL		
ACL Name	ACL Networks	Actions

If no ACLs currently exist, the dialog will only show inputs for ACL Name and ACL Networks - enter a Name and Network and click "Save Changes".

17	Add or Edit ACL			×	le
	ACL Name:	Example List			
	ACL Networks:	10.10.3.0/24	•		
			Close Save change	es	

If previous ACLs exist, a selector will be be available for "Existing ACL:".

Since we are creating a new ACL, just keep this at the default value ("Choose Existing ACL or create a new one"), and enter in the Name and Network(s) for the new ACL. Separating multiple CIDRs with a comma (,).

⁷ Add or Edit ACL		× let
Existing ACL:	Choose existing ACL or create a new one	→
ACL Name:	Example List2	
ACL Networks:	10.10.3.0/24, 192.0.0.0/24	
	Close Save change	es

When done, save the ACL by clicking "Save changes". The new ACL will be added to the Group's Applied ACL list.

Applied ACLs		×
Add or Edit ACL		
ACL Name	ACL Networks	Actions
Example List	10.10.3.0/24	Detach
Example List2	10.10.3.0/24,192.0.0.0/24	Detach

Edit an ACL

ACLs may be edited similarly to how they are created. Click the "Add or Edit ACL" button under the "Applied ACLs" module for the DNS Group. Select the ACL you wish to edit from the "Existing ACL" Selector. Then, edit the Name or Network fields as desired.

	14.42.27 00/0	0/2017 14.42.40	5	Contains Errors	Delete
)17	Add or Edit ACL				×
	Existing ACL:	Example List2			¢
	ACL Name:	Example List2			
	ACL Networks:	10.10.3.0/24,192	.0.0.0/24, 198.55.45.	0/26	
					Delete
				Close Save of	changes

When done, click "Save Changes".

Detach an ACL from a Group

Detaching an ACL removes it from the Group, but the ACL will still exist in ProVision for re-use in other Groups.

To detach an ACL, expand the "Applied ACLs" section under the desired Group, and click on the "Detach" button under the "Actions" column.

ACL Networks	Actions
10.10.3.0/24	Detach
10.10.3.0/24,192.0.0.0/24,198.55.45.0/26	Detach
	ACL Networks 10.10.3.0/24 10.10.3.0/24,192.0.0.0/24,198.55.45.0/26

The ACL will be removed from under the Group, but will remain in other Groups it exists under, as well as be selectable from the "Add ACL" window.

Delete an ACL

ACLs may be deleted through the "Edit ACL" interface. Click the "Add or Edit ACL" button under the "Applied ACLs" module for the DNS Group.

Select the ACL you wish to delete from the "Existing ACL" Selector. Then, click the red "Delete" button under the Networks field.

17	14:42:27 00/00	0/2017 14:42:40	5	Contains Errors	Delete
17	Add or Edit ACL				🗙 lete
	Existing ACL:	Example List2			÷
	ACL Name:	Example List2			
	ACL Networks:	10.10.3.0/24,192.0.0.0	0/24,198.55.45.0/2	26	
				(Delete
			С	lose Save o	changes

The ACL will be permanently deleted, and will no longer show under any Groups to which it has been attached, nor show in the "Existing ACLs" list.

Add an existing ACL to another Group

Existing ACLs may be added to as many Groups as desired. If ACLs already exist in ProVision, clicking the "Add ACL" button will give an additional option to "Create New".

To select a previously created ACL, turn the "Create New" toggle to the "OFF" position.

Add New ACL		×
Create new:	OFF	ia
Existing ACL:	Example List	¢
		Close Save changes
Push Group 📕 Schedule Pus	sh and a share a	

An "Existing ACL" list appears. Select the desired existing ACL from the list, and then click "Save changes" when done.

Additional Information

For additional information on working in DNS, see the following sections:

- Working with DNS Servers
- Configuring ISC BIND Support

- Configuring PowerDNS Support
 Configuring Secure64 Support
 Configuring DNSSEC
 Import DNS Zones
 DNS Tab